

Recording from Mobile Devices

StresStimulus can capture traffic from a mobile app. All mobile devices which allow you to set a proxy, such as an iPhone/iPad, Android, Windows phone or Blackberry are supported. The mobile device has to be connected through Wi-Fi to the same network that the StresStimulus machine is connected. In StresStimulus select **Mobile** from the record list. On the mobile device, set the network proxy settings to point to the StresStimulus machine's IP and set the port to **8888** if using Fiddler add-on or **49386** if using the standalone version (these are both the default ports and can be changed).

For more information on configuring Fiddler to capture traffic from another machine, check [this source](#). Start navigating through a test scenario on the mobile device. When recording is finished, click **Stop** in the **Recorder** or in StresStimulus. A new test case will be created.