

# Emailing Results




When a test is complete, an external report can be automatically generated and emailed to one or more email addresses. The report will be zipped and attached to the email.

## Email Settings


To provide your email settings, specify the following information in the main menu > Edit > Settings > Email tab

- **Mail Server (SMTP):** The name/address of your SMTP mail server
- **Server port:** The SMTP server port (25 default)
- **Enable SSL:** If your SMTP server requires SSL connectivity
- **Credentials:** Your SMTP credentials
- **Sender:** The sender's mail address
- **Recipient (s):** comma-separated list of email addresses to forward the emails.

Mail address


 The email address can be in the following formats:

- Display Name <Email Address>
- Email Address



Click **Send Test Email** button to send a test email to the list of recipients with the subject *StresStimulus SMTP settings test message*.

Note:

 These settings are for the test controller machine only. If the test is going to be executed on a different computer, the email settings must be configured on that machine separately.

## Enabling emailing report

The settings above are for the entire application. To enable emailing report after a test, it has to be enabled on each test individually.

In the workflow tree, go to **Advanced Options** and set **Email test result** to **Yes**.

When the test is complete, StresStimulus will send an email to the recipient(s) an email with the subject *StresStimulus Test Result* and a zipped [external report](#) in an attachment.

Note



The external report will have the default properties as described [here](#).